

Project: Sunny Beach Tote

DESIGNER: ERIN GILDAY (PATCHWORKUNDERGROUND.COM)



This sturdy tote is great for carrying to the beach or out for a day of shopping. The traditional Cathedral Window pattern with a modern twist showcases a contrasting fabric in the "window."

Project: Sunny Beach Tote

Materials

- 2 yards yellow dot (tote)
- 1 yard rust floral (inset, lining, handles)
- 1 $\frac{5}{8}$ yards iron-on fusible interfacing

Finished tote (excluding handle):
16" square

Quantities are for 44/45"-wide, 100% cotton fabrics.

Measurements include $\frac{1}{4}$ " seam allowances. Sew with right sides together unless otherwise stated.

Cut Fabrics

Cut pieces in the following order.

From yellow dot, cut:

- 2—33 $\frac{3}{4}$ " squares

From rust floral, cut:

- 2—4×23 $\frac{1}{2}$ " strips
- 2—16 $\frac{1}{2}$ " squares
- 1—11 $\frac{3}{4}$ " square (If you are using a directional print, or if you want to fussy-cut a motif for the inset square, cut the square on point.)

From fusible interfacing, cut:

- 1—16×31" rectangle
- 2—4×23 $\frac{1}{2}$ " rectangles

Assemble Tote Body

- 1.** Fold one yellow dot 33 $\frac{3}{4}$ " square in half vertically and horizontally. Finger-press folds to mark center of square; unfold. Press under $\frac{1}{4}$ " on all edges of square.
- 2.** With wrong side of square up, fold points to center; press outer folded edges. The folded unit should be about 23 $\frac{1}{2}$ " square. Hand-stitch center points together in an X (**Diagram 1**).
- 3.** Fold points of Step 2 unit to center and pin (**Diagram 2**); press outer edges. The folded square should be about 16 $\frac{1}{2}$ ".
- 4.** Repeat steps 1 through 3 with remaining yellow dot 33 $\frac{3}{4}$ " square.
- 5.** Place squares side by side, folded sides up. Open out adjacent side triangles and place squares wrong (unfolded) sides together; carefully match pressed folds and pin. Sew together along folds of open triangles to make center front seam (**Diagram 3**). Press squares open, refold triangles, and pin.
- 6.** Center and pin rust floral 11 $\frac{3}{4}$ " square over center front seam (**Diagram 4**).
- 7.** Turn a center yellow block open edge over rust fabric square; curve edge so it is about 1" wide at center and tapers to nothing at corners; pin. Repeat for remaining three edges (**Diagram 5**). Using a slip stitch, sew both curved window edges in place.
- 8.** Turn back adjacent open edges, again forming curves about 1" wide at center and tapering to nothing at corners (**Diagram 6**). Slip-stitch along both edges of curves on top half. On bottom half, slip-stitch outer curves only, sewing just through curve and one layer below it, to complete window in tote body.
- 9.** Center and fuse 16×31" interfacing rectangle to wrong side of tote body.
- 10.** Open up end triangles and fold tote body in half crosswise, matching pressed creases; pin. Stitch along creases to make center back seam of tote body (**Diagram 7**). Refold triangles and pin in place.

- 11.** Referring to **Diagram 8**, refold tote body and open up lower triangles; match creases and stitch across pressed line. Refold triangles and pin in place. Slip-stitch inner folded turnback edge (**Diagram 9**).

- 12.** Zigzag-stitch tote back triangles in place, butting folded edges, to complete tote body (**Diagram 10**).

Assemble Tote

- 1.** Fuse a 4×23 $\frac{1}{2}$ " interfacing strip to wrong side of rust floral 4×23 $\frac{1}{2}$ " strip. Press under $\frac{1}{4}$ " on each rectangle long edge, then press in half with wrong side inside to make a strap. Topstitch long edges. Add three more rows of evenly spaced topstitching. Repeat to make a second strap.
- 2.** Layer two rust floral 16 $\frac{1}{2}$ " squares; sew together side and bottom edges, leaving a 6" opening along bottom edge for turning tote right side out. Using tip of iron, carefully press seams open to make tote lining. Leave lining wrong side out.
- 3.** Referring to **Diagram 11**, pin strap raw ends to front edge of tote body with strap centered and 5" between the ends. Baste strap ends to tote body a scant $\frac{1}{4}$ " from tote edge. Repeat with second strap and tote back.
- 4.** Insert tote body inside tote lining with right sides together; straps should be between tote and lining. Align raw edges and seams. Stitch together upper edges of tote body and lining, backstitching over each strap for reinforcement.

Project: Sunny Beach Tote

5. Turn tote and lining right side out through opening in lining; pull lining out of tote. Machine-stitch opening of lining closed.
6. Insert lining back into tote and press upper edge. Topstitch $\frac{1}{8}$ " from upper edge to complete tote.




DIAGRAM 1




DIAGRAM 2




DIAGRAM 3

Project: Sunny Beach Tote




DIAGRAM 4




DIAGRAM 5




DIAGRAM 6

Project: Sunny Beach Tote




DIAGRAM 7




DIAGRAM 8




DIAGRAM 9




DIAGRAM 10




DIAGRAM 11